

Noitom Hi5 Unity SDK  
Hi5\_Unity\_SDK\_API\_1\_0\_0\_655\_16

Generated by Doxygen 1.8.13



# Contents

## 1 Namespace Index 1

1.1 Packages .....	1
--------------------	---

## 2 Class Index 3

2.1 Class List .....	3
----------------------	---

## 3 Namespace Documentation 5

3.1 HI5 Namespace Reference .....	5
-----------------------------------	---

3.1.1 Enumeration Type Documentation .....	6
--	---

3.1.1.1 Bones .....	6
---------------------	---

3.1.1.2 GloveStatus .....	7
---------------------------	---

3.1.1.3 Hand .....	7
--------------------	---

3.1.1.4 HI5_Pose .....	7
------------------------	---

3.1.1.5 MagneticStatus .....	7
------------------------------	---

3.1.1.6 OPTDeviceType .....	9 3.1.1.7
-----------------------------	-----------

PowerLevel .....	9
------------------	---

ii

CONTENTS

## 4 Class Documentation 11

4.1 HI5.HI5_BindInfoManager Class Reference .....	11
---	----

4.1.1 Detailed Description .....	12
----------------------------------	----

4.1.2 Member Function Documentation .....	12
---	----

4.1.2.1 CheckDeviceBinded() .....	12
-----------------------------------	----

4.1.2.2 IsGloveBinded() .....	12
-------------------------------	----

4.1.2.3 LoadItems() .....	13
---------------------------	----

4.1.2.4 SaveItems() .....	13
---------------------------	----

4.1.3 Member Data Documentation .....	13
---------------------------------------	----

4.1.3.1 BindInfo .....	13
------------------------	----

4.1.4 Property Documentation .....	13
------------------------------------	----

4.1.4.1 DefaultPath .....	14
---------------------------	----

4.1.4.2 IsLeftGloveBinded .....	14
---------------------------------	----

4.1.4.3 IsRightGloveBinded .....	14
----------------------------------	----

4.1.4.4 LeftID .....	14
----------------------	----

4.1.4.5 RightID .....	14
-----------------------	----

4.2 HI5.HI5_Calibration Class Reference .....	14
---	----

---

4.2.1	Detailed Description	15
4.2.2	Member Function Documentation	15
4.2.2.1	GetBindedTrackedObjectSerialNumber()	15
4.2.2.2	GetBindedTrackedObjectType()	16
4.2.2.3	GetCalibrationProgress()	16
4.2.2.4	LoadCalibrationData()	16
4.2.2.5	ResetCalibration()	17
4.2.2.6	SaveCalibrationData()	17
4.2.2.7	SetTrackedObjectBindState()	17
4.2.2.8	StartCalibration()	17
4.2.3	Member Data Documentation	19
4.2.3.1	OnCalibrationComplete	19
4.2.4	Property Documentation	19

**CONTENTS**

4.2.4.1	DefaultPath	19
4.2.4.2	IsCalibratingBPose	19
4.2.4.3	IsCalibratingPPose	19
4.3	HI5.HI5_DataTransform Class Reference	19
4.3.1	Detailed Description	20
4.3.2	Member Function Documentation	20
4.3.2.1	PushOpticalData()	20
4.3.2.2	ToUnityEulerAngles()	20
4.3.2.3	ToUnityPosition()	21
4.4	HI5.HI5_GloveStatus Class Reference	21
4.4.1	Detailed Description	22
4.4.2	Member Function Documentation	22

4.4.2.1	GetMagneticState()	22
4.4.2.2	GetPowerLevel()	22
4.4.2.3	IsGloveAvailable()	23
4.4.2.4	isGloveBPosSuccess()	23
4.4.3	Member Data Documentation	23
4.4.3.1	OnStatusChanged	23
4.4.4	Property Documentation	23
4.4.4.1	IsLeftGloveAvailable	24
4.4.4.2	IsRightGloveAvailable	24
4.4.4.3	LeftMagneticStatus	24
4.4.4.4	LeftPower	24
4.4.4.5	RightMagneticStatus	24
4.4.4.6	RightPower	24
4.4.4.7	Status	25
4.5	Hi5_Log Class Reference	25
4.5.1	Property Documentation	25
4.5.1.1	IsVisibleLog	25
4.6	HI5.HI5_Manager Class Reference	25

Generated by Doxygen

4.6.1	Detailed Description	26
4.6.2	Member Function Documentation	26
4.6.2.1	Connect()	26
4.6.2.2	Disconnect()	26
4.6.2.3	EnableBothGlovesVibration()	26
4.6.2.4	EnableLeftVibration()	27
4.6.2.5	EnableRightVibration()	27
4.6.2.6	GetGloveStatus()	27
4.6.2.7	GetHI5Source()	27

4.6.2.8	IsDongleAvailable()	28
4.6.3	Property Documentation	28
4.6.3.1	IsConnected	28
4.6.3.2	LeftOffset	28
4.6.3.3	RightOffset	28
4.7	HI5.HI5_Source Class Reference	28
4.7.1	Detailed Description	29
4.7.2	Member Function Documentation	29
4.7.2.1	GetReceivedPosition()	29
4.7.2.2	GetReceivedRotation()	29
4.7.3	Member Data Documentation	30
4.7.3.1	L_BonePos	30
4.7.3.2	L_BoneRot	30
4.7.3.3	R_BonePos	30
4.7.3.4	R_BoneRot	30
Index		31

# Chapter 1

## Namespace Index

### 1.1 Packages

Here are the packages with brief descriptions (if available):

HI5	5
-----	---







## Chapter 2

# Class Index

### 2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

<a href="#">HI5.HI5_BindInfoManager</a>	Manage the binded optical device information. ....	11
<a href="#">HI5.HI5_Calibration</a>	HI5 Calibration Class. ....	14
<a href="#">HI5.HI5_DataTransform</a>	Transform data among Unity, HI5 and HTC VIVE. ....	19
<a href="#">HI5.HI5_GloveStatus</a>	Manage all the status of <a href="#">HI5</a> glove. ....	21 <a href="#">Hi5_Log</a>
	.....	25
<a href="#">HI5.HI5_Manager</a>	Manage the basic functions of <a href="#">HI5</a> . ....	25
<a href="#">HI5.HI5_Source</a>	Manage the received data of <a href="#">HI5</a> glove .....	28 <a href="#">Class Index</a>

## Chapter 3

# Namespace Documentation

### 3.1 HI5 Namespace Reference

#### Classes

- class [HI5\\_BindInfoManager](#)  
*Manage the binded optical device information.*
- class [HI5\\_Calibration](#)  
*HI5 Calibration Class.*
- class [HI5\\_DataTransform](#)  
*Transform data among Unity, HI5 and HTC VIVE.*
- class [HI5\\_GloveStatus](#)  
*Manage all the status of HI5 glove.*
- class [HI5\\_Manager](#)  
*Manage the basic functions of HI5.*
- class [HI5\\_Source](#)  
*Manage the received data of HI5 glove*

#### Enumerations

- enum [HI5\\_Pose](#) { [HI5\\_Pose.Unknown](#) = -1, [HI5\\_Pose.BPose](#) = 0, [HI5\\_Pose.PPose](#) }  
*HI5 calibration pose.*
- enum [GloveStatus](#) {  
[GloveStatus.Unknown](#) = -1, [GloveStatus.NoDongle](#), [GloveStatus.NoGlove](#), [GloveStatus.LeftGloveAvailable](#),  
[GloveStatus.RightGloveAvailable](#), [GloveStatus.BothGloveAvailable](#) }  
*The connecting status of HI5 glove.*
- enum [Bones](#) {  
[Bones.ForeArm](#) = 0, [Bones.Hand](#) = 1, [Bones.HandThumb1](#), [Bones.HandThumb2](#),  
[Bones.HandThumb3](#), [Bones.InHandIndex](#), [Bones.HandIndex1](#), [Bones.HandIndex2](#),  
[Bones.HandIndex3](#), [Bones.InHandMiddle](#), [Bones.HandMiddle1](#), [Bones.HandMiddle2](#),  
[Bones.HandMiddle3](#), [Bones.InHandRing](#), [Bones.HandRing1](#), [Bones.HandRing2](#),  
[Bones.HandRing3](#), [Bones.InHandPinky](#), [Bones.HandPinky1](#), [Bones.HandPinky2](#), [Bones.HandPinky3](#),  
[Bones.NumOfHI5Bones](#) }  
*HI5 bones reference.*
- enum [OPTDeviceType](#) { [OPTDeviceType.Unknown](#) = -1, [OPTDeviceType.HTC\\_VIVE\\_Tracker](#), [OPTDeviceType.HTC\\_VIVE\\_Controller](#) }

---

*The type of optical tracked device.*

- enum [PowerLevel](#) { [PowerLevel.Unknown](#) = -1, [PowerLevel.Full](#) = 0, [PowerLevel.Normal](#), [PowerLevel.Low](#) }

*The different level of the glove power.*

- enum [MagneticStatus](#) { [MagneticStatus.Unknown](#) = -1, [MagneticStatus.Good](#) = 0, [MagneticStatus.Fair](#), [MagneticStatus.Bad](#) }

*Magnetic field environment status.*

- enum [Hand](#) { [Hand.LEFT](#) = 0, [Hand.RIGHT](#) }

*The left or right type of hand.*

### 3.1.1 Enumeration Type Documentation

#### 3.1.1.1 Bones

enum [HI5.Bones](#) [strong]

[HI5](#) bones reference.

##### Enumerator

ForeArm	The fore arm joint.
Hand	The hand joint.
HandThumb1	The metacarpal joint of thumb finger.
HandThumb2	The proximal joint of thumb finger.
HandThumb3	The distal joint of thumb finger.
InHandIndex	The metacarpal joint of index finger.
HandIndex1	The proximal joint of index finger.
HandIndex2	The middle joint of index finger.
HandIndex3	The distal joint of index finger.
InHandMiddle	The metacarpal joint of middle finger.
HandMiddle1	The proximal joint of middle finger.
HandMiddle2	The middle joint of middle finger.
HandMiddle3	The distal joint of middle finger.
InHandRing	The metacarpal joint of ring finger.
HandRing1	The proximal joint of ring finger.
HandRing2	The middle joint of ring finger.

---

---

HandRing3	The distal joint of ring finger.
InHandPinky	The metacarpal joint of pinky finger.
HandPinky1	The proximal joint of pinky finger.
HandPinky2	The middle joint of pinky finger.
HandPinky3	The distal joint of pinky finger.
NumOfHI5Bones	The number of joints of HI5 bones.

6

Namespace Documentation

**3.1 HI5 Namespace Reference**

7

**3.1.1.2 GloveStatus**

enum [HI5.GloveStatus](#) [strong] The connecting status of [HI5](#) glove.

**Enumerator**

Unknown	The unknown status of glove.
NoDongle	No dongle connected.
NoGlove	No glove connected.
LeftGloveAvailable	The left glove is available.
RightGloveAvailable	The right glove is available.
BothGloveAvailable	Both gloves are available.

**3.1.1.3 Hand**

enum [HI5.Hand](#) [strong]

The left or right type of hand.

**Enumerator**

LEFT	Left hand.
RIGHT	Right hand.

**3.1.1.4 HI5\_Pose**

enum [HI5.HI5\\_Pose](#) [strong]

[HI5](#) calibration pose.

**Enumerator**

Unknown	Unknown pose.
---------	---------------

---

---

BPose	Buddha Pose
PPose	Pinch Pose.

#### 3.1.1.5 MagneticStatus

enum [HI5.MagneticStatus](#) [strong]

Generated by Doxygen

Magnetic field environment status.

Generated by Doxygen

### 3.1 HI5 Namespace Reference

9

#### Enumerator

Unknown	Unknown status .
Good	Status is good.
Fair	Status is fair.
Bad	Status is bad.

#### 3.1.1.6 OPTDeviceType

enum [HI5.OPTDeviceType](#) [strong] The type of  
optical tracked device.

#### Enumerator

Unknown	Unknown type.
HTC_VIVE_Tracker	Type of HTC VIVE tracker.
HTC_VIVE_Controller	Type of HTC VIVE controller.

#### 3.1.1.7 PowerLevel

enum [HI5.PowerLevel](#) [strong]

The different level of the glove power.

#### Enumerator

Unknown	Unknown power level.
---------	----------------------

---

---

Full	Full power level.
Normal	Normal power level.
Low	Low power level.

Generated by Doxygen

---



## Chapter 4

# Class Documentation

### 4.1 HI5.HI5\_BindInfoManager Class Reference

Manage the binded optical device information.

#### Classes

- class **DeviceInfo**

*Both binded tracked device information.*

#### Static Public Member Functions

- static bool [IsGloveBinded](#) ([Hand](#) handType)  
*Check the specific glove is binded on any optical device.*
- static bool [CheckDeviceBinded](#) ([Hand](#) handType, string serialNumber)  
*Check whether the device was binded on left or right glove.*
- static void [SaveItems](#) ()  
*Save the binded optical device serial number of both hand locally.*
- static bool [LoadItems](#) ()  
*Load the binded optical device serial number of both hand locally.*

#### Static Public Attributes

- static HI5\_BindInfo [BindInfo](#) = new HI5\_BindInfo()  
*The instance of HI5\_Bind Info class, saved binded optical device informations.*

#### Properties

- static int [LeftID](#) [get, set]  
*Get or set the ID of tracked device binded on left glove.*
- static int [RightID](#) [get, set]  
*Get or set the ID of tracked device binded on right glove.*



- static bool `IsLeftGloveBinded` [get]  
*Get the bind state of left glove. True, the left glove is binded on one optical device. False, the left glove is not binded any optical devcie.*
- static bool `IsRightGloveBinded` [get]  
*Get the bind state of right glove. True, the right glove is binded on one optical device. False, the right glove is not binded any optical devcie.*
- static string `DefaultPath` [get]  
*Get the default path of saving and reading binded device information file.*

#### 4.1.1 Detailed Description

Manage the binded optical device information.

#### 4.1.2 Member Function Documentation

##### 4.1.2.1 `CheckDeviceBinded()`      static      bool

HI5.HI5\_BindInfoManager.CheckDeviceBinded (

`Hand handType`, string  
`serialNumber` ) [static]

Check whether the device was binded on left or right glove.

##### Parameters

<code>handType</code>	The type of <code>HI5.Hand</code> .
<code>serialNumber</code>	The serial number of the device.

##### Returns

True, the device was binded on specific glove. False, the device was not binded on specific glove.

##### 4.1.2.2 `IsGloveBinded()`      static      bool

HI5.HI5\_BindInfoManager.IsGloveBinded (

`Hand handType` ) [static] Check the specific

glove is binded on any optical device.

#### 4.1 HI5.HI5\_BindInfoManager Class Reference

##### Parameters

<code>handType</code>	The type of <code>HI5.Hand</code>
-----------------------	-----------------------------------

##### Returns

True, the specific glove is binided. False, the specific glove is not binided.

#### 4.1.2.3 LoadItems()

static bool HI5.HI5\_BindInfoManager.LoadItems ( ) [static] Load the binded optical device  
serail number of both hand locally.

##### Returns

True, successfully load the device serial number. False, failed load the device serial number.

#### 4.1.2.4 SaveItems()

static void HI5.HI5\_BindInfoManager.SaveItems ( ) [static] Save the binded optical device  
serail number of both hand locally. b\_pos save

### 4.1.3 Member Data Documentation

#### 4.1.3.1 BindInfo

HI5\_BindInfo HI5.HI5\_BindInfoManager.BindInfo = new HI5\_BindInfo() [static] The instance of HI5\_Bind Info class,  
saved binded optical device informations.

### 4.1.4 Property Documentation

#### 4.1.4.1 DefaultPath

string HI5.HI5\_BindInfoManager.DefaultPath [static], [get]

Get the default path of saving and reading binded device information file.

#### 4.1.4.2 IsLeftGloveBinded

bool HI5.HI5\_BindInfoManager.IsLeftGloveBinded [static], [get]

Get the bind state of left glove. True, the left glove is binded on one optical device. False, the left glove is not binded any  
optical devcie.

#### 4.1.4.3 IsRightGloveBinded

bool HI5.HI5\_BindInfoManager.IsRightGloveBinded [static], [get]

Get the bind state of right glove. True, the right glove is binded on one optical device. False, the right glove is not binded any optical devcie.

#### 4.1.4.4 LeftID

int HI5.HI5\_BindInfoManager.LeftID [static], [get], [set] Get or set the ID of tracked

device binded on left glove.

#### 4.1.4.5 RightID

int HI5.HI5\_BindInfoManager.RightID [static], [get], [set] Get or set the ID of tracked

device binded on right glove.

## 4.2 HI5.HI5\_Calibration Class Reference

HI5 Calibration Class.

### 4.2 HI5.HI5\_Calibration Class Reference

#### Static Public Member Functions

- static void [ResetCalibration](#) ()  
*Call it before doing B-pose calibration.*
- static void [StartCalibration](#) (HI5\_Pose pose)  
*Start B/P-pose calibration.*
- static int [GetCalibrationProgress](#) (HI5\_Pose pose)  
*Get the percent of B/P-pose calibration.*
- static bool [SaveCalibrationData](#) ()  
*Save calibration data to default path.*
- static string [GetBindedTrackedObjectSerialNumber](#) (Hand handType)  
*Get the serial number of tracked object binded on left/right hand.*
- static [OPTDeviceType](#) [GetBindedTrackedObjectType](#) (Hand handType)  
*Get the type of tracked object binded on left/right hand.*
- static void [SetTrackedObjectBindState](#) (Hand handType, string serialNumber, [OPTDeviceType](#) deviceType)  
*Set the serial number of tracked object binded on left/right hand. This function called only after loading the PairInfo file successfully.*
- static bool [LoadCalibrationData](#) () *Load the previous calibration data.*

## Static Public Attributes

- static Action< [HI5\\_Pose](#) > [OnCalibrationComplete](#)  
*Call it when B-pose or P-pose calibration complete.*

## Properties

- static bool [IsCalibratingBPose](#) [get] *Is doing calibration B-pose or not.*
- static bool [IsCalibratingPPose](#) [get] *Is doing calibration P-pose or not.*
- static string [DefaultPath](#) [get]  
*Get the default path of saving the calibration data.*
- static string [DefaultPathAndName](#) [get]

### 4.2.1 Detailed Description

[HI5](#) Calibration Class.

### 4.2.2 Member Function Documentation

#### 4.2.2.1 GetBindedTrackedObjectSerialNumber()

HI5.HI5\_Calibration.GetBindedTrackedObjectSerialNumber ( [Hand](#)  
*handType* ) [static]

Get the serial number of tracked object binded on left/right hand.

#### Parameters

<i>handType</i>	The type of <a href="#">HI5.Hand</a> .
-----------------	--

#### Returns

The serial number of device.

#### 4.2.2.2 GetBindedTrackedObjectType()

static [OPTDeviceType](#) HI5.HI5\_Calibration.GetBindedTrackedObjectType ( [Hand](#)  
*handType* ) [static]

Get the type of tracked object binded on left/right hand.

#### Parameters

<i>handType</i>	The type of <a href="#">HI5.Hand</a> .
-----------------	--

#### Returns

The type of optical device.

#### 4.2.2.3 GetCalibrationProgress() static int

HI5.HI5\_Calibration.GetCalibrationProgress

( [HI5\\_Pose](#) pose ) [static]

Get the percent of B/P-pose calibration.

##### Parameters

<i>pose</i>	The type of calibration pose by <a href="#">HI5.HI5_Pose</a> .
-------------	--

##### Returns

The progress of the related calibration. The value is provided by percent number.

#### 4.2.2.4 LoadCalibrationData()

static bool HI5.HI5\_Calibration.LoadCalibrationData ( ) [static] Load

the previous calibration data.

#### 4.2 HI5.HI5\_Calibration Class Reference

##### Returns

True, successfully loaded the calibration data. False, failed loaded the calibration data.

#### 4.2.2.5 ResetCalibration()

static void HI5.HI5\_Calibration.ResetCalibration ( ) [static] Call it before doing B-pose

calibration.

#### 4.2.2.6 SaveCalibrationData()

static bool HI5.HI5\_Calibration.SaveCalibrationData ( ) [static] Save calibration data to default path.

##### Returns

True, successfull saved calibration data to default path. False, failed saved calibration data to default path.

#### 4.2.2.7 SetTrackedObjectBindState() static void

HI5.HI5\_Calibration.SetTrackedObjectBindState (

[Hand](#) handType, string  
serialNumber,  
[OPTDeviceType](#) deviceType ) [static]

Set the serial number of tracked object binded on left/right hand. This function called only after loading the PairInfo file successfully.

**Parameters**

<i>handType</i>	The type of <a href="#">HI5.Hand</a> .
<i>serialNumber</i>	The serial number of the binded device. Input by System.String.
<i>deviceType</i>	The type of <a href="#">HI5.OPTDeviceType</a> .

**4.2.2.8 StartCalibration()**    static    void

HI5.HI5\_Calibration.StartCalibration ( [HI5\\_Pose](#)

*pose* ) [static]

Start B/P-pose calibration.

**4.3 HI5.HI5\_DataTransform Class Reference****Parameters**

<i>pose</i>	The type of calibration pose by <a href="#">HI5.HI5_Pose</a> .
-------------	--

**4.2.3 Member Data Documentation****4.2.3.1 OnCalibrationComplete**

Action<[HI5\\_Pose](#)> HI5.HI5\_Calibration.OnCalibrationComplete [static] Call it when B-pose or P-pose calibration complete.

**4.2.4 Property Documentation****4.2.4.1 DefaultPath**

string HI5.HI5\_Calibration.DefaultPath [static], [get] Get the default path of saving the calibration data.

**4.2.4.2 IsCalibratingBPose**

bool HI5.HI5\_Calibration.IsCalibratingBPose [static], [get] Is doing calibration B-pose or not.

#### 4.2.4.3 IsCalibratingPPose

bool `HI5.HI5_Calibration.IsCalibratingPPose` [static], [get] Is doing calibration P-pose or not.

### 4.3 HI5.HI5\_DataTransform Class Reference

Transform data among Unity, Hi5 and HTC VIVE.

#### Static Public Member Functions

- static `Vector3 ToUnityPosition` (`Vector3 pos`)  
*Transform received [HI5](#) position data to Unity position data.*
- static `Vector3 ToUnityEulerAngles` (`Vector3 eulerAngles`)  
*Transform received [HI5](#) rotation data in euler angles to Unity euler angles.*
- static void `PushOpticalData` (string `serialNumber`, `OPTDeviceType` `deviceType`, `Vector3 pos`, `Quaternion rot`)  
*Push received optical devices data into HI5 data stream.*

#### 4.3.1 Detailed Description

Transform data among Unity, Hi5 and HTC VIVE.

#### 4.3.2 Member Function Documentation

##### 4.3.2.1 `PushOpticalData()` static void

`HI5.HI5_DataTransform.PushOpticalData` (

string *serialNumber*,  
[OPTDeviceType](#) *deviceType*,  
 Vector3 *pos*,  
 Quaternion *rot* ) [static]

Push received optical devices data into HI5 data stream.

##### Parameters

<i>serialNumber</i>	The serial number of the device. Input by System.String.
<i>deviceType</i>	The type of <a href="#">HI5.OPTDeviceType</a> .
<i>pos</i>	The position data of the device by UnityEngine.Vector3.
<i>rot</i>	The rotation data of the device by UnityEngine.Quaternion.

##### 4.3.2.2 `ToUnityEulerAngles()` static Vector3

`HI5.HI5_DataTransform.ToUnityEulerAngles` ( Vector3

*eulerAngles* ) [static]

Transform received [HI5](#) rotation data in euler angles to Unity euler angles.

#### Parameters

<i>eulerAngles</i>	Received HI5 euler angles by UnityEngine.Vector3.
--------------------	---

#### 4.4 HI5.HI5\_GloveStatus Class Reference

#### Returns

Euler angles in Vector3.

##### 4.3.2.3 ToUnityPosition() static Vector3

HI5.HI5\_DataTransform.ToUnityPosition ( Vector3 *pos* )

[static]

Transform received [HI5](#) position data to Unity position data.

#### Parameters

<i>pos</i>	Received HI5 position data by UnityEngine.Vector3.
------------	--

#### Returns

Position data in Vector3.

## 4.4 HI5.HI5\_GloveStatus Class Reference

Manage all the status of [HI5](#) glove.

### Public Member Functions

- void **StartCalibrationBpos** ()
- bool **isGloveBPosSuccess** ()  
*Get the Calibration Bpos Result.*
- [PowerLevel](#) **GetPowerLevel** ([Hand](#) handType)  
*Get the power level of left/right glove.*
- [MagneticStatus](#) **GetMagneticState** ([Hand](#) handType)  
*Get the magnetic field status of left/right glove.*
- bool **IsGloveAvailable** ([Hand](#) handType) *Check whether left/right glove is available*

### Public Attributes

- Action< [GloveStatus](#) > **OnStatusChanged** *Call when glove connecting status changed.*

### Properties

- [PowerLevel](#) **LeftPower** [get]  
*The power level of left glove.*

- [PowerLevel](#) **RightPower** [get]



---

*The power level of right glove.*

- [MagneticStatus LeftMagneticStatus](#) [get]  
*The magnetic field status around left glove.*
- [MagneticStatus RightMagneticStatus](#) [get]  
*The magnetic field status around right glove.*
- [bool IsLeftGloveAvailable](#) [get]  
*Check whether the left glove is available.*
- [bool IsRightGloveAvailable](#) [get]  
*Check whether the right glove is available.*
- [GloveStatus Status](#) [get]  
*Get the current glove status.*

#### 4.4.1 Detailed Description

Manage all the status of [HI5](#) glove.

#### 4.4.2 Member Function Documentation

##### 4.4.2.1 GetMagneticState()

[MagneticStatus](#) HI5.HI5\_GloveStatus.GetMagneticState (  
[Hand](#) handType )

Get the magnetic field status of left/right glove.

##### Parameters

<i>handType</i>	The type of <a href="#">HI5.Hand</a> .
-----------------	--

##### Returns

The related magnetic field status of left/right glove.

##### 4.4.2.2 GetPowerLevel()

[PowerLevel](#) HI5.HI5\_GloveStatus.GetPowerLevel (  
[Hand](#) handType )

Get the power level of left/right glove.

#### 4.4 HI5.HI5\_GloveStatus Class Reference

##### Parameters

<i>handType</i>	The type of <a href="#">HI5.Hand</a> .
-----------------	--

##### Returns

The related power level of left/right glove.

---

#### 4.4.2.3 IsGloveAvailable() bool

HI5.HI5\_GloveStatus.IsGloveAvailable

( [Hand](#) *handType* )

Check whether left/right glove is available

##### Parameters

<i>handType</i>	The type of <a href="#">HI5.Hand</a> .
-----------------	--

##### Returns

True, the specific glove is available. False, the specific glove is inavailable.

#### 4.4.2.4 isGloveBPosSuccess()

bool HI5.HI5\_GloveStatus.isGloveBPosSuccess ( ) Get the Calibration Bpos

Result.

### 4.4.3 Member Data Documentation

#### 4.4.3.1 OnStatusChanged

Action<[GloveStatus](#)> HI5.HI5\_GloveStatus.OnStatusChanged Call when glove connecting status changed.

### 4.4.4 Property Documentation

#### 4.4.4.1 IsLeftGloveAvailable

bool HI5.HI5\_GloveStatus.IsLeftGloveAvailable [get] Check whether the left glove is available.

#### 4.4.4.2 IsRightGloveAvailable

bool HI5.HI5\_GloveStatus.IsRightGloveAvailable [get] Check whether the right glove is available.

---

#### 4.4.4.3 LeftMagneticStatus

**MagneticStatus** HI5.HI5\_GloveStatus.LeftMagneticStatus [get] The magnetic field status around left glove.

#### 4.4.4.4 LeftPower

**PowerLevel** HI5.HI5\_GloveStatus.LeftPower [get] The power level of left glove.

#### 4.4.4.5 RightMagneticStatus

**MagneticStatus** HI5.HI5\_GloveStatus.RightMagneticStatus [get] The magnetic field status around right glove.

#### 4.4.4.6 RightPower

**PowerLevel** HI5.HI5\_GloveStatus.RightPower [get]

The power level of right glove.

### 4.5 Hi5\_Log Class Reference

#### 4.4.4.7 Status

**GloveStatus** HI5.HI5\_GloveStatus.Status [get] Get the current glove status.

## 4.5 Hi5\_Log Class Reference

### Static Public Member Functions

- static void **Log** (string logContent)
- static void **LogError** (string logContent)
- static void **LogWarning** (string logContent)

### Properties

- static bool **IsVisibleLog** [get, set] *Get whether the Hi5 Log is visible.*

### 4.5.1 Property Documentation

#### 4.5.1.1 IsVisibleLog

bool Hi5\_Log.IsVisibleLog [static], [get], [set] Get whether the Hi5 Log is visible.

## 4.6 HI5.HI5\_Manager Class Reference

Manage the basic functions of [HI5](#).

### Static Public Member Functions

- static void [Connect](#) () *Connect the Hi5 device.*
- static void [Disconnect](#) ()  
*Disconnect the Hi5 device.*
- static [HI5\\_GloveStatus](#) [GetGloveStatus](#) ()  
*Get the instance of [HI5\\_GloveStatus](#) class.*
- static [HI5\\_Source](#) [GetHI5Source](#) ()  
*Get the instance of [HI5\\_Source](#) class.*
- static bool [IsDongleAvailable](#) ()  
*Check whether the [HI5](#) dongle is available.*
- static void [EnableLeftVibration](#) (int time)  
*Control the vibration on left glove.*
- static void [EnableRightVibration](#) (int time) *Control the vibration on right glove.*
- static void [EnableBothGlovesVibration](#) (int leftTime, int rightTime) *Control the vibration on both gloves.*

### Properties

- static bool [IsConnected](#) [get] *Get whether the Hi5 dongle is connected.*
- static Vector3 [LeftOffset](#) [get]  
*Get the left glove position offset related to binded optical device.*
- static Vector3 [RightOffset](#) [get]  
*Get the right glove position offset related to binded optical device.*

#### 4.6.1 Detailed Description Manage

the basic functions of [HI5](#).

#### 4.6.2 Member Function Documentation

##### 4.6.2.1 Connect()

static void HI5.HI5\_Manager.Connect ( ) [static] Connect the Hi5 device.

#### 4.6.2.2 Disconnect()

static void HI5.HI5\_Manager.DisConnect ( ) [static] Disconnect the HI5 device.

#### 4.6.2.3 EnableBothGlovesVibration()

static void HI5.HI5\_Manager.EnableBothGlovesVibration ( int *leftTime*,  
int *rightTime* ) [static]

Control the vibration on both gloves.

##### Parameters

<i>leftTime</i>	Input the vibration time by milliseconds on left glove.
<i>rightTime</i>	Input the vibration time by milliseconds on right glove.

#### 4.6 HI5.HI5\_Manager Class Reference

#### 4.6.2.4 EnableLeftVibration() static void

HI5.HI5\_Manager.EnableLeftVibration ( int *time* )

[static]

Control the vibration on left glove.

##### Parameters

<i>time</i>	Input the vibration time by milliseconds.
-------------	---

#### 4.6.2.5 EnableRightVibration() static void

HI5.HI5\_Manager.EnableRightVibration ( int *time* )

[static]

Control the vibration on right glove.

##### Parameters

<i>time</i>	Input the vibration time by milliseconds.
-------------	---

#### 4.6.2.6 GetGloveStatus()

static [HI5\\_GloveStatus](#) HI5.HI5\_Manager.GetGloveStatus ( ) [static] Get the instance of [HI5\\_GloveStatus](#) class.

##### Returns

[HI5\\_GloveStatus](#) class instance

#### 4.6.2.7 GetHI5Source()

static [HI5\\_Source](#) HI5.HI5\_Manager.GetHI5Source ( ) [static] Get the instance of [HI5\\_Source](#) class.

##### Returns

[HI5\\_Source](#) class instance [4.6.2.8 IsDongleAvailable\(\)](#)

static bool HI5.HI5\_Manager.IsDongleAvailable ( ) [static] Check whether the [HI5](#) dongle is available.

##### Returns

True, the [HI5](#) dongle is available. False, the [HI5](#) dongle is inavailable.

### 4.6.3 Property Documentation

#### 4.6.3.1 IsConnected

bool HI5.HI5\_Manager.IsConnected [static], [get] Get whether the HI5 dongle is connected.

#### 4.6.3.2 LeftOffset

Vector3 HI5.HI5\_Manager.LeftOffset [static], [get]

Get the left glove position offset related to binded optical device.

#### 4.6.3.3 RightOffset

Vector3 HI5.HI5\_Manager.RightOffset [static], [get]

Get the right glove position offset related to binded optical device.

## 4.7 HI5.HI5\_Source Class Reference

Manage the received data of [HI5](#) glove

### Public Member Functions

- Vector3 [GetReceivedRotation](#) (int boneIndex, [Hand](#) handType) Get received rotation data of left/right hand specific bones. The index is referenced to Bones enum.
- Vector3 [GetReceivedPosition](#) (int boneIndex, [Hand](#) handType)

---

Get received position data of left/right hand specific bones. The index is referenced to Bones enum.

## 4.7 HI5.HI5\_Source Class Reference

### Public Attributes

- Vector3 [ ] [L\\_BonePos](#) = new Vector3[(int)[Bones.NumOfHI5Bones](#)]  
The position data array of left hand bones. The array is referenced to *Bones* enum.
- Vector3 [ ] [R\\_BonePos](#) = new Vector3[(int)[Bones.NumOfHI5Bones](#)]  
The position data array of right hand bones. The array is referenced to *Bones* enum.
- Vector3 [ ] [L\\_BoneRot](#) = new Vector3[(int)[Bones.NumOfHI5Bones](#)]  
The rotation data array of left hand bones. The array is referenced to *Bones* enum.
- Vector3 [ ] [R\\_BoneRot](#) = new Vector3[(int)[Bones.NumOfHI5Bones](#)]  
The rotation data array of right hand bones. The array is referenced to *Bones* enum.

### 4.7.1 Detailed Description

Manage the received data of [HI5](#) glove

### 4.7.2 Member Function Documentation

#### 4.7.2.1 GetReceivedPosition()

Vector3 HI5.HI5\_Source.GetReceivedPosition ( int  
    *boneIndex*,  
    [Hand](#) *handType* )

Get received position data of left/right hand specific bones. The index is referenced to *Bones* enum.

#### Parameters

<i>boneIndex</i>	The index of the specific bone. Reference by <a href="#">HI5.Bones</a> .
<i>handType</i>	The type of <a href="#">HI5.Hand</a> .

#### Returns

The received position of specific bone by `UnityEngine.Vector3`.

#### 4.7.2.2 GetReceivedRotation()

Vector3 HI5.HI5\_Source.GetReceivedRotation ( int  
    *boneIndex*,  
    [Hand](#) *handType* )

Get received rotation data of left/right hand specific bones. The index is referenced to *Bones* enum.

---

**Parameters**

<i>boneIndex</i>	The index of the specific bone. Reference by <a href="#">HI5.Bones</a> .
<i>handType</i>	The type of <a href="#">HI5.Hand</a> .

**Returns**

The received rotation of specific bone by `UnityEngine.Vector3`.

### 4.7.3 Member Data Documentation

#### 4.7.3.1 L\_BonePos

`Vector3 [] HI5.HI5_Source.L_BonePos = new Vector3[(int)Bones.NumOfHI5Bones]` The position data array of left hand bones. The array is referenced to `Bones` enum.

#### 4.7.3.2 L\_BoneRot

`Vector3 [] HI5.HI5_Source.L_BoneRot = new Vector3[(int)Bones.NumOfHI5Bones]` The rotation data array of left hand bones. The array is referenced to `Bones` enum.

#### 4.7.3.3 R\_BonePos

`Vector3 [] HI5.HI5_Source.R_BonePos = new Vector3[(int)Bones.NumOfHI5Bones]` The position data array of right hand bones. The array is referenced to `Bones` enum.

#### 4.7.3.4 R\_BoneRot

`Vector3 [] HI5.HI5_Source.R_BoneRot = new Vector3[(int)Bones.NumOfHI5Bones]`

The rotation data array of right hand bones. The array is referenced to `Bones` enum.



# Index

## BindInfo

HI5::HI5\_BindInfoManager, [13](#)

## Bones

HI5, [6](#)

## CheckDeviceBinded

HI5::HI5\_BindInfoManager, [12](#)

## Connect

HI5::HI5\_Manager, [26](#)

## DefaultPath

HI5::HI5\_BindInfoManager, [13](#) HI5::HI5\_Calibration, [19](#)

## DisConnect

HI5::HI5\_Manager, [26](#)

EnableBothGlovesVibration HI5::HI5\_Manager, [26](#)

## EnableLeftVibration

HI5::HI5\_Manager, [27](#) EnableRightVibration

HI5::HI5\_Manager, [27](#) GetBindedTrackedObjectSerialNumber

HI5::HI5\_Calibration, [15](#)

GetBindedTrackedObjectType HI5::HI5\_Calibration, [16](#)

## GetCalibrationProgress

HI5::HI5\_Calibration, [16](#)

## GetGloveStatus

HI5::HI5\_Manager, [27](#) GetHI5Source

HI5::HI5\_Manager, [27](#)

## GetMagneticState

HI5::HI5\_GloveStatus, [22](#) GetPowerLevel

HI5::HI5\_GloveStatus, [22](#)

## GetReceivedPosition

HI5::HI5\_Source, [29](#) GetReceivedRotation

HI5::HI5\_Source, [29](#)

## GloveStatus HI5,

[6](#)

## HI5, [5](#)

Bones, [6](#)

GloveStatus, [6](#)

HI5\_Pose, [7](#)

Hand, [7](#)

MagneticStatus, [7](#)

OPTDeviceType, [9](#)

PowerLevel, [9](#)

HI5.HI5\_BindInfoManager, [11](#)

HI5.HI5\_Calibration, [14](#)

HI5.HI5\_DataTransform, [19](#)

HI5.HI5\_GloveStatus, [21](#)

HI5.HI5\_Manager, [25](#)

HI5.HI5\_Source, [28](#)

HI5::HI5\_BindInfoManager

BindInfo, [13](#)

CheckDeviceBinded, [12](#)

DefaultPath, [13](#)

IsGloveBinded, [12](#)

IsLeftGloveBinded, [14](#)

IsRightGloveBinded, [14](#)

LeftID, [14](#)

LoadItems, [13](#) RightID,

[14](#)

SaveItems, [13](#)

HI5::HI5\_Calibration

DefaultPath, [19](#)

GetBindedTrackedObjectSerialNumber, [15](#)

GetBindedTrackedObjectType, [16](#)

GetCalibrationProgress, [16](#)

IsCalibratingBPose, [19](#)

IsCalibratingPPose, [19](#)

LoadCalibrationData, [16](#)

OnCalibrationComplete, [19](#)

ResetCalibration, [17](#)

SaveCalibrationData, [17](#)

SetTrackedObjectBindState, [17](#)

StartCalibration, [17](#)

HI5::HI5\_DataTransform

PushOpticalData, [20](#)

ToUnityEulerAngles, [20](#)

ToUnityPosition, [21](#)

HI5::HI5\_GloveStatus

GetMagneticState, [22](#)

GetPowerLevel, [22](#)

IsGloveAvailable, [23](#) isGloveBPosSuccess, [23](#)

IsLeftGloveAvailable, [23](#)

IsRightGloveAvailable, [24](#)

LeftMagneticStatus, [24](#)

LeftPower, [24](#)

OnStatusChanged, [23](#)

RightMagneticStatus, [24](#)

RightPower, [24](#)

Status, [24](#)

HI5::HI5\_Manager

- 
- Connect, [26](#)
  - Disconnect, [26](#)
  - EnableBothGlovesVibration, [26](#)
  - EnableLeftVibration, [27](#)
  - EnableRightVibration, [27](#)
  - GetGloveStatus, [27](#)
  - GetHI5Source, [27](#)
  - IsConnected, [28](#)
  - IsDongleAvailable, [27](#)
  - LeftOffset, [28](#)
  - RightOffset, [28](#)
  - HI5::HI5\_Source
    - GetReceivedPosition, [29](#)
    - GetReceivedRotation, [29](#)
    - L\_BonePos, [30](#)
    - L\_BoneRot, [30](#)
    - R\_BonePos, [30](#)
    - R\_BoneRot, [30](#)
  - HI5\_Pose
    - HI5, [7](#) Hand
    - HI5, [7](#)
  - Hi5\_Log, [25](#)
    - IsVisibleLog, [25](#)
  - IsCalibratingBPose
    - HI5::HI5\_Calibration, [19](#) IsCalibratingPPose
    - HI5::HI5\_Calibration, [19](#)
  - IsConnected
    - HI5::HI5\_Manager, [28](#) IsDongleAvailable
    - HI5::HI5\_Manager, [27](#)
  - IsGloveAvailable
    - HI5::HI5\_Manager, [28](#)
  - LeftPower
    - HI5::HI5\_GloveStatus, [24](#)
  - LoadCalibrationData
    - HI5::HI5\_Calibration, [16](#)
  - LoadItems
    - HI5::HI5\_BindInfoManager, [13](#)
  - MagneticStatus HI5, [7](#)
  - OPTDeviceType
    - HI5, [9](#)
  - OnCalibrationComplete
    - HI5::HI5\_Calibration, [19](#)
  - OnStatusChanged
    - HI5::HI5\_GloveStatus, [23](#)
  - PowerLevel
    - HI5, [9](#)
  - PushOpticalData
    - HI5::HI5\_DataTransform, [20](#)
  - R\_BonePos
    - HI5::HI5\_Source, [30](#) R\_BoneRot
    - HI5::HI5\_Source, [30](#)
  - ResetCalibration
    - HI5::HI5\_Calibration, [17](#)
  - RightID
    - HI5::HI5\_BindInfoManager, [14](#)
  - RightMagneticStatus
    - HI5::HI5\_GloveStatus, [24](#)
  - RightOffset
    - HI5::HI5\_Manager, [28](#)

HI5::HI5\_GloveStatus, [23](#) isGloveBPosSuccess  
    HI5::HI5\_GloveStatus, [23](#)  
IsGloveBinded  
    HI5::HI5\_BindInfoManager, [12](#)  
IsLeftGloveAvailable  
    HI5::HI5\_GloveStatus, [23](#)  
IsLeftGloveBinded  
    HI5::HI5\_BindInfoManager, [14](#)  
IsRightGloveAvailable  
    HI5::HI5\_GloveStatus, [24](#)  
IsRightGloveBinded  
    HI5::HI5\_BindInfoManager, [14](#)  
IsVisibleLog  
    Hi5\_Log, [25](#)  
  
L\_BonePos  
    HI5::HI5\_Source, [30](#) L\_BoneRot HI5::HI5\_Source,  
    [30](#)  
LeftID  
    HI5::HI5\_BindInfoManager, [14](#)  
LeftMagneticStatus  
    HI5::HI5\_GloveStatus, [24](#)  
LeftOffset

RightPower  
    HI5::HI5\_GloveStatus, [24](#)  
  
SaveCalibrationData  
    HI5::HI5\_Calibration, [17](#)  
SaveItems  
    HI5::HI5\_BindInfoManager, [13](#)  
SetTrackedObjectBindState  
    HI5::HI5\_Calibration, [17](#)  
StartCalibration  
    HI5::HI5\_Calibration, [17](#)  
Status  
    HI5::HI5\_GloveStatus, [24](#)  
  
ToUnityEulerAngles  
    HI5::HI5\_DataTransform, [20](#)  
ToUnityPosition  
    HI5::HI5\_DataTransform, [21](#)

---

